# Submitting Test Results to CGI/ASP Script

# Introduction

Lectora has the ability to capture student information such as names, email addresses, test answers, and test results so that you can manage your courses and your students more efficiently and effectively. Connecting Lectora to your database requires CGI or ASP scripting, which directs the data to a database. Because databases are different, custom CGI/ASP scripting must be written for each Lectora-to-Database connection.

The information on the following pages is intended to help you design a CGI/ASP script. Combining the information offered here with the expertise of your database manager and IT or ISP manager, you should be able to develop an effective connection between Lectora and your database.

Please remember this is an example of CGI and ASP script. A programmer knowledgeable in CGI/ASP Scripting and Database integration over the Internet/Intranet should perform the integration between Lectora and the database.

### 1. Variables in Lectora

This page shows Lectora's variable structure

**<u>2. Add a CGI/ASP Script to Lectora</u>** This page describes how to integrate a CGI Script in to Lectora for both tests and forms.

#### **3. Script Examples**

This page gives an example of a CGI and ASP Script which receives test results.

### 4. Connecting to a Database

This section explains how to use scripts with a database and includes an MS Access and ASP example.

Please keep in mind that the sample script offered is just an example. It is a model on which you can base your own custom-written CGI/ASP script.

If you have any questions about this information contained here, please feel welcome to call Trivantis Technical Services at (513)852-6700.



# 1. Variables in Lectora

Lectora provides the ability to submit test and form results to a CGI/ASP application. This is done by selecting the Submit Test to CGI/ASP Program option in a test's properties dialog and also in the Submit form to CGI/ASP program in the form properties, and subsequently specifying a CGI/ASP program to which results will be sent in the area provided. Use Name Value Pairs to get the values from Lectora.

Name	Value
Name	The students name
Email	The students email address
TestName	The name of the test
NumQuestions	The number of questions in the test
PassingGrade	The value specified in the Lowest Passing score field on the
	Results tab of the
	Test's properties. If the output of the test is sent to XML, then the
	passing score itself is not sent, but the result of passing or failing is
	represented by the XML notation <passed></passed> or <failed></failed> .
Score	The total score of the test (if it could be scored)
TrueFalse	The number of True/False questions correct/in the test
MultipleChoice	The number of multiple choice questions correct/in the test
XML	An XML formatted collection of the above parameters (see XML
	example below)

Parameters which are sent to a CGI/ASP application via **test submission**:

The next section would iterate for as many questions as were in the test. In each of the following the X is replaced by the actual number of the question (i.e. Question1, Answer1):

Name	Value
QuestionX	The text of the question
AnswerX	The students answer to the question
CorrectAnswerX	The correct answer to the question
QuestionTypeX	The type of the question (TRUEFALSE=1, MULTCHOICE=2,
	SHORTANSWER=3, ESSAY=4)

Additional Variables may be sent by selecting, "include all variable values upon submission":

Name	Value
BrowserType	The name of the browser used to view the title. When in
	run/preview mode, this value will be Lectora, when in a CD
	publish this value will be LectoraViewer.
CurrentChapterName,	Displays the current name of the title, chapter, section, or
CurrentPageName,	page the user is viewing (respectfully.) This value is set to
CurrentSectionName,	unknown if not currently being used.
CurrentTitleName	
CurrentDate	Contains today's date in the form Month, Day, Year. For
	example: January 1, 2003.
CurrentTime	Has the current time in the form hh:mm AM/PM. For
	example: 2:21 PM.



ElaspedTime	The total time the user has been viewing the title.			
PageInChapter,	The current page number with the chapter/title the user is on			
PageInTitle				
PagesInChapter,	Total number of pages in the current title/chapter			
PagesInTitle				
Platform	The operating system the user is running the title from.			
	(Win32, MacPPC, Windows NT)			
PublishDate	The date that the title was published.			

Note that any variables you create will also be sent as well, if including all variables on submission.



# 2. Add CGI/ASP to Lectora

Many problems stem from people not knowing what to put in the "submit results to" field on the test properties. You may send the results to a specific web url using "http:// " and then type the full path to script program.

If you include your script with the rest of your title, you may simply use a relative path. For example, if you were using ASP, and the test processing page was called "processResults.asp", and it was in a directory called "myasp", the submit results to line would say "myasp/processResults.asp".

### Through a test

🙎 Test Propert	ties			X	
Response General	When Complet Background	ed/Passed	When Cano Content	celed/Failed Results	
Grade	<ul> <li>✓ Show test results to student after end of test</li> <li>✓ Grade the test</li> <li>✓ Show only the score of the test, not the questions and answers</li> <li>Lowest Passing Score</li> <li>75 ★</li> <li>Results Submission</li> </ul>				
	ail Results of Test iubmit in XML format		Test to CGI progr od POST 💌	ram	
Submit results to: myasp/processResults.cgi					
<ul> <li>Prompt the student for their name to identify the test</li> <li>Include all variable values in submission</li> <li>Show the student a success dialog if submission is successful</li> </ul>					
		OK	Cancel	Help	

Or if you were using ASP, and their test processing page was called

"processResults.asp", and the page was at the same level as the index.html page, the submit results to line would say.

P Test Properties	×			
Response When Completed/Passed When Canc General Background Inherit Content	eled/Failed   Results			
Show test results to student after end of test Grade the test Show only the score of the test, not the questions and answers Lowest Passing Score   75   Results Submission   Email Results of Test   Submit in XML format   Method   POST				
Submit results to: processResults.cgi				
<ul> <li>Prompt the student for their name to identify the test</li> <li>Include all variable values in submission</li> <li>Show the student a success dialog if submission is successful</li> </ul>				
OK Cancel Help				



	Form name:	Form_1			
	Retain values Submission	of all form el	ements betwe	en sessions	
	Email form	L format		form to CGI pro od POST	gram
9	Submit results to:	processRe	sults.asp		
□ Ir	nclude all variable	values in for	n submission		
▼ S	how the student a	a success dia	log if submiss	ion is successf	ul

The above example will submit all variables associated with the form (radio buttons, entry fields, ect) to processResults.asp, which is in the same folder as the rest of the title files.

If you wish to include other values with the form you may click on the "Parameters" tab and add each value individually. See the example below.

🛿 Form Properties				
General Parameters Response Fly In / Fly Out				
When submitting a form, additional name/value pairs may be specified that will be included in the submission.				
Parameter Name	Parameter Value			
StudentID	VAR(StudentId)			
Add	Edit Remove			
OK Cancel Help				

Here, we will send the parameter StudentID and it will contain the value of the variable StudentID from the title. This is done by setting it's value to VAR(StudentID). You may set any parameter to a Lectora variable using the VAR(*LectoraVariableName*) function.



## 3. Script Example

# **Example ASP Script**

\*\* -- This script is for example purposes only -- \*\* <%@ Language=VBScript %> <% 'Get the parameters posted from the test' testname=Request.form("TestName") score=Request.form("Score") user=Request.form("name") email=Request.form("email") numQuestions=Request.form("NumQuestions") passingGrade=Request.form("PassingGrade") trueFalse=Request.form( "TrueFalse" ) multipleChoice=Request.form( "MultipleChoice" ) 'Validate that this is actually from a Lectora test' if testname="" Or score="" Or user="" Or email="" Or numQuestions="" Or passingGrade="" Or trueFalse="" Or multipleChoice="" then Response.Write "<html>" Response.Write "<head><title>Failure</title></head>" Response.Write "<body>" Response.Write "STATUS=500" Response.Write "<br> Response.Write "Could not parse test results due to a parameter error." Response.Write "</body></html>" else 'Write the results to a file' 'This could be a database or any kind of object store, but' 'to keep it simple, we will just use a flat text file' fileName = "C:\" & testname & ".log" 'Open the results file for append' Const ForReading = 1, ForWriting = 2, ForAppending = 8 Set objFSO = CreateObject("Scripting.FileSystemObject") Set objInFile = objFSO.OpenTextFile( fileName, ForAppending, True ) 'Write the results' objInFile.WriteLine( Date & ", " & Time & ", " & user & ", " & email & ", " & score ) 'Close results file' objInFile.Close Set objInFile = Nothing Set objFSO = Nothing 'The response is optional, it is good for debugging' Response.Write "<html>" Response.Write "<head><title>Success</title></head>" Response.Write "<body>" Response.Write "STATUS=200" Response.Write "<br> Response.Write "Success." Response.Write "</body></html>" end if %>





# **Example CGI Script**

#!perl use CGI; q = new CGI;#get the parameters passed to the script \$name = \$q->param('name'); \$testName = \$q->param('TestName'); \$numQuestions = \$q->param('NumQuestions'); \$passingGrade = \$q->param('PassingGrade'); \$score = \$q->param('Score'); if( \$testName eq "" || \$numQuestions eq "" ) { print "Content-type: text/html\n\n"; print "<html>"; print "<head><title>Failure</title></head>"; print "<body>"; print "STATUS=500"; print "<br>"; print "Could not parse test results due to a parameter error."; print "</body></html>"; exit 0: #get the current time (\$sec,\$min,\$hour,\$mday,\$mon,\$year,\$wday,\$yday,\$isdst) = localtime(time); \$year = \$year + 1900; mon = mon + 1;\$currtime = "\$year-\$mon-\$mday \$hour:\$min:\$sec";

#### 

#### 



```
$qval = $q->param( $qst );
$aval = $q->param( $ans );
print TESTDATA "$qst: $qval\n";
print TESTDATA "$ans: $aval\n";
$index += 1;
```

}



## 4. Connecting to a Database

Now that the basics of script files have been covered, a more advanced type script may be used to store the results inside of a database. The included zip file **'Database\_example.zip'** contains a sample Access database and ASP scripts to store test results.

There are 3 files here. There is an asp script called **saveresults.asp** which takes the test results and stores them to the database. This is the file you link to inside of your test properties (as mentioned in the 'through a test' section above.)

The second asp script called **viewresults.asp** can be viewed in the web browser and will show all the data from the database inside a table. Both of these scripts need to be placed on the web server.

The next step is to take the database file **TestResults.mdb** and place it in a new directory on the web server called c:\database. Now you must link to the database using ODBC.

- Go into the control panel, click administrative tools, click Data Sources (ODBC)
- Go into the "system DSN" tab and click add new data source
- Select "driver do Microsoft Access .mdb" as the driver
- Click finish, for data source name use "TestResults"
- Select the database file under c:\database\TestResults.mdb
- Click OK

ODBC Microsoft Access Setup	? 🗙
Data Source Name: TestResults	ОК
Description: Lectora test results	Cancel
Database: C:\Database\TestResults.mdb	<u>H</u> elp
Select <u>Create</u> <u>R</u> epair <u>Compact</u>	<u>A</u> dvanced
- System Database	
• None	
C Database:	
System Database	<u>O</u> ptions>>

You should now have a simple working database to store test results.

